

# DUVET

Designed by Robert Kaufman Fabrics      Featuring  
[www.robertkaufman.com](http://www.robertkaufman.com)

Valori Wells  
Blueprint Basics WIDE



Finished size: 64" x 86"

Pattern Level: Enthusiastic Novice

"I am a total beginner and want to learn more!"

ROBERT KAUFMAN  
F A B R I C S

For questions about this pattern, please email [Patterns@RobertKaufman.com](mailto:Patterns@RobertKaufman.com).

## Fabric and Supplies Needed

Fabric amounts based on yardage that is 108" wide.

Color	Fabric	Name/SKU	Yardage	Color	Fabric	Name/SKU	Yardage
	A	AVWX-16064-81 TURQUOISE	4 yards			Copyright 2016, Robert Kaufman For individual use only - Not for resale	

You will also need:  
5-6" of 1" wide hook and loop tape

### Notes Before You Begin

- Read through all of the instructions before beginning.
- All of the seam allowances are 1/4" unless otherwise noted.
- Press seam allowances open unless otherwise noted.
- Right sides together has been abbreviated to RST.
- Remember to measure twice and cut once!

### Cutting Instructions

#### From Fabric A, cut:

Two 65-1/2" x WOF pieces



<<Tip: Because the pieces are so big, designate a front and back now, and pin a label on each piece.>>

Cut the **front** at 89-3/4" x 65-1/2", and the **back** at 93-3/4" x 65-1/2" long.

### Sew the Duvet

1. Hem the front piece along the bottom edge by folding up 1-1/2" to the wrong side and then folding up another 1-1/2". Sew along the upper fold.

2. Hem the back piece along the bottom edge by folding up 1/2" then another 1/2". Sew along the upper edge. Fold the bottom edge up 6" toward the wrong side, and baste the two side edges so the folded bottom edge makes a pocket to hold the duvet when it's inserted.



3. French seam the sides of the duvet cover by aligning front and back pieces wrong sides together, and sewing a 1/4" seam along both sides. Press the seam well to either side, then turn the duvet inside out, so that it is right sides together. Carefully press again, working the seam between thumb and forefinger where necessary to flatten it. Sew along both side seams with a 1/2" seam allowance, and open the cover back up to be right side out.

4. Now repeat the French seam process for the top edge (1/4" seam with wrong sides together, press, turn, press, 1/2" seam with right sides together, turn right side out, press.)


<<Note: If you are experienced with French seams, you may combine Steps 3 and 4, sewing along both sides and the top edge, stopping with needle down to pivot at the corners.>>

5. With right sides together, sew along the edges of the folded bottom edge about 10" from either side, leaving approximately 45" open in the middle of the bottom and backstitching at the beginning and end.

6. Inside the opening, center 1" squares of hook tape on the front, and put the corresponding loop tape square on the pocket of the back.

<<Note: Make sure to only sew onto the pocket, not **through** the pocket!>>

Space out two more sets of hook and loop tape on either side of the center piece (about 7"-8" apart). Sew hooks on the front and loops on the back pocket.



7. Trim threads, then insert duvet. Make sure the bottom of the duvet slides into the pocket on the back. Then close the velcro, drape on a bed, and cuddle up!